

Integrate STM32™ CubeMX® into Atollic® TrueSTUDIO®





Requirements

Assumptions:

- Atollic® TrueSTUDIO® v.4.3.1 (or later)is installed on your computer.
- The latest available version of STM32 CubeMX Eclipse plug-in (part-number: "ST SW-STM32095")

Constraints

 Atollic tries to assure that succeeding versions of Atollic TrueSTUDIO works with the latest version of STM32 CubeMX. Contact support@atollic.com if you have any questions.







Quick summary

Summary of installation steps:

- Download STM32 CubeMX from ST webpage
- Install the plug-in using the Eclipse installation system (P2)
- Open STM32CubeMX perspective to start working!




STSW-STM32095 STM32C ×



Embedded Passion


Download STM32 CubeMX Eclipse plug-in



Navigate to:

http://www.st.com/web/en/catalog/tools/PF257931


- Scroll down to "Sample & Buy":
 - Download the plugin by clicking Download







Install STM32 CubeMX using P2




- Start Atollic® TrueSTUDIO®
- Help → Install New Software (P2)
- Click the Add button to point out a plug-in to be installed in TrueSTUDIO
- · Choose:
 - Archive
 - Browse for downloaded zip-file (stswstm32095.zip)
 - Click OK
 - Name field: STM32 CubeMX
 - Click OK





Choose items



 Select packages (all) to be installed and click *Next*


• On *Install details* page simply click *Next*







Finish installation of CubeMX




- Review the license agreement, select I accept...
- Click Finish
- Plug-in is being installed
- A notification about unsigned content will showup, click OK
- Click Yes to re-launch TrueSTUDIO!






Open PEx perspective



- Work with STM32 CubeMX® in its own perspective by clicking:
- Window → Open Perspective
- Other...
- STM32CubeMX
- OK



More information:

www.atollic.com

EUROPE & WORLDWIDE

Atollic AB

Science Park

Gjuterigatan 7

SE-553 18 Jönköping

Sweden

+46 36 19 60 50

info@atollic.com

USA & AMERICAS

Atollic Inc.

241 Boston Post Road West

First Floor

Marlborough

Massachusetts 01752

+1 (508) 657-1158

sales.usa@atollic.com

